

# Dovecot maildir Migration



Baustelle / Work in Progress

## Quellen

## Commands

```
doveadm backup -v -u xenadmin@meinekleinefarm.net remote:mail.mgs-ullrich.de
```

```
doveadm -v -o imapc_host=hostname -o imapc_port=993 -o imapc_ssl=imaps -o  
imapc_ssl_ca_dir=/etc/ssl -o imapc_ssl_verify=yes -o  
imapc_master_username=masteruser -o imapc_password=password -o  
imapc_username=xenadmin@meinekleinefarm.net backup -R -u  
xenadmin@meinekleinefarm.net imapc:
```

```
doveadm -v -o imapc_host=192.168.223.10 -o imapc_port=993 -o imapc_ssl=imaps  
-o imapc_ssl_verify=no -o imapc_master_username=master -o imapc_password=XXX  
-o imapc_username=xenadmin@meinekleinefarm.net backup -R -u  
xenadmin@meinekleinefarm.net imapc:
```

```
doveadm -v -o imapc_host=192.168.223.10 -o imapc_port=993 -o imapc_ssl=imaps  
-o imapc_ssl_verify=no -o imapc_master_user=dovecot-master -o  
imapc_password=XXX -o imapc_username=xenadmin@meinekleinefarm.net backup -R  
-u xenadmin@meinekleinefarm.net imapc:
```

```
doveadm -v -o imapc_host=192.168.223.10 -o imapc_port=993 -o imapc_ssl=imaps  
-o imapc_ssl_verify=no -o imapc_password=XXX -o  
imapc_username=xenadmin@meinekleinefarm.net backup -R -u  
xenadmin@meinekleinefarm.net imapc:
```

```
doveadm -o imapc_host=192.168.223.10 -o imapc_port=993 -o mail_fsync=never -  
o mail_fsync=never -o imapc_features=rfc822.size -o imapc_features=fetch-  
headers -o imapc_ssl=imaps -o imapc_ssl_verify=no -o imapc_password=XXX -o  
imapc_username=xenadmin@meinekleinefarm.net -D backup -R -u  
xenadmin@meinekleinefarm.net imapc:
```

From:  
<https://dokuwiki.meinekleinefarm.net/> - Meine kleine Dokumentation

Permanent link:  
[https://dokuwiki.meinekleinefarm.net/doku.php?id=dovecot\\_maildir\\_migration&rev=1479851215](https://dokuwiki.meinekleinefarm.net/doku.php?id=dovecot_maildir_migration&rev=1479851215)

Last update: 2016/11/22 21:46



