

Dovecot maildir Migration



Quellen

Commands

```
doveadm backup -v -u xenadmin@meinekleinefarm.net remote:mail.mgs-ullrich.de
```

```
doveadm -v -o imapc_host=hostname -o imapc_port=993 -o imapc_ssl=imaps -o
imapc_ssl_ca_dir=/etc/ssl -o imapc_ssl_verify=yes -o
imapc_master_username=masteruser -o imapc_password=password -o
imapc_username=xenadmin@meinekleinefarm.net backup -R -u
xenadmin@meinekleinefarm.net imapc:
```

```
doveadm -v -o imapc_host=192.168.223.10 -o imapc_port=993 -o imapc_ssl=imaps
-o imapc_ssl_verify=no -o imapc_master_username=master -o imapc_password=XXX
-o imapc_username=xenadmin@meinekleinefarm.net backup -R -u
xenadmin@meinekleinefarm.net imapc:
```

```
doveadm -v -o imapc_host=192.168.223.10 -o imapc_port=993 -o imapc_ssl=imaps
-o imapc_ssl_verify=no -o imapc_master_user=dovecot-master -o
imapc_password=XXX -o imapc_username=xenadmin@meinekleinefarm.net backup -R
-u xenadmin@meinekleinefarm.net imapc:
```

```
doveadm -v -o imapc_host=192.168.223.10 -o imapc_port=993 -o imapc_ssl=imaps
-o imapc_ssl_verify=no -o imapc_password=XXX -o
imapc_username=xenadmin@meinekleinefarm.net backup -R -u
xenadmin@meinekleinefarm.net imapc:
```

```
doveadm -o imapc_host=192.168.223.10 -o imapc_port=993 -o mail_fsync=never -
o mail_fsync=never -o imapc_features=rfc822.size -o imapc_features=fetch-
headers -o imapc_ssl=imaps -o imapc_ssl_verify=no -o imapc_password=XXX -o
imapc_username=xenadmin@meinekleinefarm.net -D backup -R -u
xenadmin@meinekleinefarm.net imapc:
```

From: <https://host.docker.internal:552/> - **Meine kleine Dokumentation**

Permanent link: https://host.docker.internal:552/doku.php?id=dovecot_maildir_migration&rev=1479851665

Last update: **2016/11/22 21:54**



