

Dovecot maildir Migration



Baustelle / Work in Progress

Quellen

TESTS

```
doveadm backup -v -u xenadmin@meinekleinefarm.net remote:mail.mgs-ullrich.de
```

```
doveadm -v -o imapc_host=hostname -o imapc_port=993 -o imapc_ssl=imaps -o  
imapc_ssl_ca_dir=/etc/ssl -o imapc_ssl_verify=yes -o  
imapc_master_username=masteruser -o imapc_password=password -o  
imapc_username=xenadmin@meinekleinefarm.net backup -R -u  
xenadmin@meinekleinefarm.net imapc:
```

```
doveadm -v -o imapc_host=192.168.223.10 -o imapc_port=993 -o imapc_ssl=imaps  
-o imapc_ssl_verify=no -o imapc_master_username=master -o imapc_password=XXX  
-o imapc_username=xenadmin@meinekleinefarm.net backup -R -u  
xenadmin@meinekleinefarm.net imapc:
```

```
doveadm -v -o imapc_host=192.168.223.10 -o imapc_port=993 -o imapc_ssl=imaps  
-o imapc_ssl_verify=no -o imapc_master_user=dovecot-master -o  
imapc_password=XXX -o imapc_username=xenadmin@meinekleinefarm.net backup -R  
-u xenadmin@meinekleinefarm.net imapc:
```

```
doveadm -v -o imapc_host=192.168.223.10 -o imapc_port=993 -o imapc_ssl=imaps  
-o imapc_ssl_verify=no -o imapc_password=XXX -o  
imapc_username=xenadmin@meinekleinefarm.net backup -R -u  
xenadmin@meinekleinefarm.net imapc:
```

```
doveadm -o imapc_host=192.168.223.10 -o imapc_port=993 -o mail_fsyc=never -  
o mail_fsyc=never -o imapc_features=rfc822.size -o imapc_features=fetch-  
headers -o imapc_ssl=imaps -o imapc_ssl_verify=no -o imapc_password=XXX -o  
imapc_username=xenadmin@meinekleinefarm.net -D backup -R -u  
xenadmin@meinekleinefarm.net imapc:
```

===== FUNKTIONIERT =====

<code bash>

```
doveadm -o imapc_host=192.168.223.10 -o imapc_port=993 -o mail_fsyc=never -  
o mail_fsyc=never -o imapc_features=rfc822.size -o imapc_features=fetch-  
headers -o imapc_ssl=imaps -o imapc_ssl_verify=no -o  
imapc_master_user=dovecot-master@admin.loc -o imapc_password=XXX -o  
imapc_username=xenadmin@meinekleinefarm.net -D backup -R -u
```

```
xenadmin@meinekleinefarm.net imapc:
```

```
doveadm -o imapc_host=192.168.223.10 -o imapc_port=993 -o mail_fsyc=never -  
o mail_fsyc=never -o imapc_features=rfc822.size -o imapc_features=fetch-  
headers -o imapc_ssl=imaps -o imapc_ssl_verify=no -o  
imapc_master_user=dovecot-master@admin.loc -o imapc_password=XXX -o  
imapc_username=info@mgs-ullrich.de -D backup -R -u info@mgs-ullrich.de  
imapc:
```

From:
<https://host.docker.internal:552/> - **Meine kleine Dokumentation**

Permanent link:
https://host.docker.internal:552/doku.php?id=dovecot_maildir_migration&rev=1479941631

Last update: **2016/11/23 22:53**

