

Seafile Server Migration von Ubuntu 14.04 LTS -> Debian 8 Jessie

Quellen

1. https://manual.seafiler.com/maintain/backup_recovery.html
2. <https://unwahrscheinlichkeitsdrive.de/2015/02/07/seafiler-migration/>

Auf dem "alten" Server

```
<<Alle seafiler Dienste stoppen>>
```

```
mysqldump -h localhost -u root -p seafiler_ccnet-db > ccnet-db.sql  
mysqldump -h localhost -u root -p seafiler_seafiler-db > seafiler-db.sql  
mysqldump -h localhost -u root -p seafiler_seahub-db > seahub-db.sql
```

```
scp -r -P 22 /root/seafiler_db/ccnet-db.sql root@192.168.1.2:/root  
scp -r -P 22 /root/seafiler_db/seafiler-db.sql root@192.168.1.2:/root  
scp -r -P 22 /root/seafiler_db/seahub-db.sql root@192.168.1.2:/root
```

```
cd /home/seafiler/seafiler-server
```

```
tar -czvf - * | ssh -p 22 root@192.168.1.2 'tar -xhvf - -C /opt/seafiler/'
```

Auf dem "neuen" Server

```
apt install python2.7 libpython2.7 python-setuptools python-imaging \  
python-ldap python-mysqldb python-memcache python-urllib3 \  
memcached python-memcache sudo -y  
adduser --disabled-login --home /opt/seafiler --shell /bin/false --gecos  
"Seafiler" seafiler  
chown seafiler:root /opt/seafiler -R  
  
mysql -u root -p
```

```
CREATE USER 'seafiler'@'localhost' IDENTIFIED BY 'PASSWORD1';
```

```
CREATE DATABASE `seafiler_ccnet-db`;  
CREATE DATABASE `seafiler_seafiler-db`;  
CREATE DATABASE `seafiler_seahub-db`;
```

```
GRANT ALL privileges ON `seafiler_ccnet-db`.* TO 'seafiler'@'localhost';  
GRANT ALL privileges ON `seafiler_seafiler-db`.* TO 'seafiler'@'localhost';  
GRANT ALL privileges ON `seafiler_seahub-db`.* TO 'seafiler'@'localhost';
```

```
flush privileges;
```

```
mysql -u root -p seafile_ccnet-db < /root/ccnet-db.sql  
mysql -u root -p seafile_seafile-db < /root/seafile-db.sql  
mysql -u root -p seafile_seahub-db < /root/seahub-db.sql
```

```
nano /opt/seafile/conf/ccnet.conf  
nano /opt/seafile/conf/seafile.conf  
nano /opt/seafile/conf/seahub_settings.py  
nano /opt/seafile/ccnet/seafile.ini  
su seafile  
cd /opt/seafile/seafile-server-latest/  
./seaf-fsck.sh  
./seaf.sh start  
./seahub.sh start-fastcgi  
exit
```

```
mkdir /var/www/html/meinekleinefarm.net/seafile  
nano /etc/apache2/sites-available/files.meinekleinefarm.net.conf
```

[files.meinekleinefarm.net.conf](#)

```
<VirtualHost *:80>  
    ServerName files.meinekleinefarm.net  
    Redirect permanent / https://files.meinekleinefarm.net/  
</VirtualHost>  
  
<IfModule mod_ssl.c>  
<VirtualHost *:443>  
    ServerAdmin webmaster@meinekleinefarm.net  
    ServerName files.meinekleinefarm.net  
    ServerAlias files.meinekleinefarm.net  
  
    DocumentRoot /var/www/html/meinekleinefarm.net/seafile  
  
    SSLEngine on  
    SSLCertificateFile  
/etc/letsencrypt/live/meinekleinefarm.net/fullchain.pem  
    SSLCertificateKeyFile  
/etc/letsencrypt/live/meinekleinefarm.net/privkey.pem  
  
    Alias /media /opt/seafile/seafile-server-latest/seahub/media  
  
    <Location /media>  
        ProxyPass !  
        Require all granted  
    </Location>  
  
    RewriteEngine On
```

```
# seafile fileserver
ProxyPass /seafhttp http://127.0.0.1:8082
ProxyPassReverse /seafhttp http://127.0.0.1:8082
RewriteRule ^/seafhttp - [QSA,L]

# seahub
SetEnvIf Request_URI . proxy-fcgi-pathinfo=unescape
SetEnvIf Authorization "(.*)" HTTP_AUTHORIZATION=$1
ProxyPass / fcgi://127.0.0.1:8000/
</VirtualHost>
</IfModule>
```

```
a2ensite files.meinekleinefarm.net.conf
service apache2 reload
```

Seafile Server Init Script

```
nano /etc/init.d/seafile-server
```

seafile-server

```
#!/bin/sh

### BEGIN INIT INFO
# Provides:          seafile-server
# Required-Start:    $local_fs $remote_fs $network mysql
# Required-Stop:     $local_fs
# Default-Start:     2 3 4 5
# Default-Stop:      0 1 6
# Short-Description: Starts Seafile Server
# Description:       starts Seafile Server
### END INIT INFO

# Change the value of "user" to linux user name who runs seafile
user=seafile

# Change the value of "seafile_dir" to your path of seafile
# installation
# usually the home directory of $user
seafile_dir=/opt/seafile
script_path=${seafile_dir}/seafile-server-latest
seafile_init_log=${seafile_dir}/logs/seafile.init.log
seahub_init_log=${seafile_dir}/logs/seahub.init.log

# Change the value of fastcgi to true if fastcgi is to be used
fastcgi=true
```

```
# Set the port of fastcgi, default is 8000. Change it if you need
different.
fastcgi_port=8000

#
# Write a polite log message with date and time
#
echo -e "\n\n About to perform $1 for seafile at `date -Iseconds` \n "
>> ${seafile_init_log}
echo -e "\n\n About to perform $1 for seahub at `date -Iseconds` \n "
>> ${seahub_init_log}

case "$1" in
    start)
        sudo -u ${user} ${script_path}/seafile.sh ${1} >>
        ${seafile_init_log}
        if [ $fastcgi = true ];
        then
            sudo -u ${user} ${script_path}/seahub.sh ${1}-
            fastcgi ${fastcgi_port} >> ${seahub_init_log}
        else
            sudo -u ${user} ${script_path}/seahub.sh ${1}
            >> ${seahub_init_log}
        fi
        ;;
    restart)
        sudo -u ${user} ${script_path}/seafile.sh ${1} >>
        ${seafile_init_log}
        if [ $fastcgi = true ];
        then
            sudo -u ${user} ${script_path}/seahub.sh ${1}-
            fastcgi ${fastcgi_port} >> ${seahub_init_log}
        else
            sudo -u ${user} ${script_path}/seahub.sh ${1}
            >> ${seahub_init_log}
        fi
        ;;
    stop)
        sudo -u ${user} ${script_path}/seahub.sh ${1} >>
        ${seahub_init_log}
        sudo -u ${user} ${script_path}/seafile.sh ${1} >>
        ${seafile_init_log}
        ;;
    *)
        echo "Usage: /etc/init.d/seafile-server
        {start|stop|restart}"
        exit 1
        ;;
esac
```

```
mkdir -p /opt/seafiler/logs/  
chmod +x /etc/init.d/seafiler-server  
update-rc.d seafiler-server defaults
```

Garbage Collecting Unused Blocks on Seafiler Server

```
nano /opt/seafiler/sfs_gc.sh
```

```
<hidden /etc/init.d/seafiler-server -edit> <code bash seafiler-server>
```

From:

<https://host.docker.internal:552/> - **Meine kleine Dokumentation**

Permanent link:

https://host.docker.internal:552/doku.php?id=seafiler_server_migration

Last update: **2017/04/10 14:38**

