

Dovecot



Baustelle / Work in Progress

Setup

```
apt install -t jessie-backports dovecot-core dovecot-imapd dovecot-lmtpd -y  
cp -arf /etc/dovecot/conf.d/ /etc/dovecot/conf.d.BAK  
cd /etc/dovecot/conf.d  
  
mkdir -p /var/mail/vhosts/meinekleinefarm.net  
mkdir -p /var/mail/vhosts/mgs-ullrich.de  
groupadd -g 5000 vmail  
useradd -r -g vmail -u 5000 vmail -d /var/mail/vhosts -c "Dovecot virtual  
mail user"  
chown -R vmail:vmail /var/mail/vhosts/
```

10-mail.conf

```
nano 10-mail.conf
```

- mail_location = maildir:/var/mail/vhosts/%d/%n

10-master.conf

```
nano 10-master.conf
```

- service imap-login {
 inet_listener imap {
 #port = 143
 }
 inet_listener imaps {
 port = 993
 ssl = yes
 }

 service lmtp {
 unix_listener /var/spool/postfix/private/dovecot-lmtp {
 group = postfix

```
user = postfix
mode = 0666
}

service auth {
# Postfix smtp-auth
unix_listener /var/spool/postfix/private/auth {
    mode = 0666
    user = postfix
    group = postfix
}
```

10-auth.conf

nano 10-auth.conf

- disable_plaintext_auth = yes
Today however many people use SSL/TLS, and there's no problem with sending unencrypted password inside SSL secured connections.
auth_mechanisms = plain login

#!include auth-system.conf.ext
#!include auth-sql.conf.ext
#!include auth-ldap.conf.ext
!include auth-passwdfile.conf.ext
#!include auth-checkpassword.conf.ext
#!include auth-vpopmail.conf.ext
#!include auth-static.conf.ext

auth-passwdfile.conf.ext

nano auth-passwdfile.conf.ext

- # Authentication for passwd-file users. Included from 10-auth.conf.

passwd-like file with specified location.
<doc/wiki/AuthDatabase.PasswdFile.txt>

passdb {
 driver = passwd-file
 args = scheme=SHA512-CRYPT username_format=%u /etc/dovecot/dovecot-users
}

```
userdb {
  driver = static
  args = uid=vmail gid=vmail home=/var/mail/vhosts/%d/%n
}
```

Dovecot Users PasswdFile

```
doveadm pw -l  
doveadm pw -s SHA512-CRYPT  
nano ./dovecot-users
```


10-ssl.conf

nano **10-ssl.conf**

- `ssl = required`
`ssl_cert = </etc/letsencrypt/live/meinekleinefarm.net/fullchain.pem`
`ssl_key = </etc/letsencrypt/live/meinekleinefarm.net/privkey.pem`

10-logging.conf

```
nano 10-logging.conf
```

- log path = /var/log/dovecot.log

Setup logrotate

```
nano /etc/logrotate.d/dovecot
```

```
• /var/log/dovecot*.log {
    missingok
    notifempty
    delaycompress
    sharedscripts
    postrotate
        dovecadm log reopen
    endscript
}
```

Fin

```
systemctl restart dovecot
```

From:
<https://dokuwiki.meinekleinefarm.net/> - **Meine kleine Dokumentation**



Permanent link:
https://dokuwiki.meinekleinefarm.net/doku.php?id=dovecot_installation&rev=1478725686

Last update: **2016/11/09 21:08**